Remote Desktop Gateway setting

This explains how to setup Remote Desktop Connection client to use remotegate.uno.edu to access machines on campus from off campus. This connects you to our network and then attempts to connect you to the machine.

Look for the *Remote Desktop Connection* under the Start Menu in the folder Windows Accessories. If you have Windows 10 you can type remote desktop connection in the search area. Once you have found Remote Desktop Connection click on it to launch it. Type the full server or computer name *(i.e. remote.uno.edu)* you would like to connect to in the Computer field.

🌄 Remote	Desktop Connection	-		×
	Remote Desktop Connection			
Computer: User name: You will be a:	uno.edu None specified sked for credentials when you connect.	~		
Show O	ptions	Connect	Hel	p

Click the *Show Options* (Alt-O) to display more settings, then click on the *Advanced* tab. Click on the *Settings* button for "Connect from anywhere" section.

Nemote Desktop Connection	_		\times	
Remote Desktop Connection				
General Display Local Resources Experience	Advanced			
Server authentication				
Server authentication verifies that you intended remote computer. The streng to connect is determined by your syste	Server authentication verifies that you are connecting to the intended remote computer. The strength of the verification required to connect is determined by your system security policy.			
If server authentication fails:				
Warn me			\sim	
Connect from anywhere				
Configure settings to connect through when I am working remotely.	Remote Deskt	top Gateway		
Hide Options Connect		He	lp	

Select the radio button Use these RD Gateway server settings.

In Server Name type remotegate.uno.edu

In "Logon method:" select Ask for password.

Make sure the check box Bypass RD Gateway for local address is checked.

Check the box Use my RD Gateway credentials for the remote computer. This will allow you to only have to type your username and password once.

Semote Desktop Connection – – ×					
Remote Desktop					
ND Gateway Server Settings					
Remote Desktop					
Connection					
Connection settings					
Automatically detect RD Gateway server settings					
Use these RD Gateway server settings:					
Server name: remotegate.uno.edu					
Logon method: Ask for password (NTLM) ~					
Bypass RD Gateway server for local addresses					
O Do not use an RD Gateway server					
Logon settings					
User name: None specified					
You will be asked for credentials when you connect to this RD Gateway server.					
Use my RD Gateway credentials for the remote computer					
OK Cancel					

Click OK.

You may want to look at the tab for *Display* or *Local Resources* to adjust screen size, printing or access to your local drives.

Click Connect to connect to the server.